# Spout SDK

A software development kit for texture sharing between applications.

spout.zeal.co

# Update beta release 2.007

June 2018

Spout is now used by many applications and so it is important that any changes are tested thoroughly before release.

A beta test package has been created as a branch to the Spout2 GitHub repository which contains source, files, demonstration programs and binaries for testing. A library for Processing is also included.

Refer to the branch readme for further details and examples.

# 1. Changes for existing projects

Existing projects need only minor changes and additions and, after attention to the items below, will rebuild and function as before. They can be tested in advance of the 2.007 release and other changes can be explored.

Check "Frame count" on with *SpoutSettings* to enable the frame counting functions.

# 1.1 Legacy OpenGL

Functions with legacy OpenGL code can be removed so that the SDK is compliant with more recent versions of OpenGL by disabling a define in "SpoutCommon.h".

```
#define legacyOpenGL
```

The following functions are then disabled:

DrawSharedTexture DrawToSharedTexture

#### 1.2 New files

To update existing projects, add the following four files:

spoutFrameCount.h spoutFrameCount.cpp spoutUtils.h spoutUtils.cpp

# 1.3 using std namespace removed

```
The statement:
```

```
using namespace std;
```

has been removed from the Spout SDK to give programmers the option for including this or not. If you receive warnings about missing std functions with existing projects, you can include this statement in your header files.

# 1.4 Changed functions

```
bool GetSenderName(int index, char* Sendername, int MaxSize = 256);
Changed to :
bool GetSender(int index, char* Sendername, int MaxSize = 256);
GetSenderName now returns the connected sender name.
const char * GetSenderName();
```

The GetImageSize function has been removed from SpoutReceiver.

RemovePadding has been added to SpoutReceiver for correction of image stride where necessary.

Registry functions have been moved to the SpoutUtils namespace and arguments revised as detailed below.

#### 1.5 CPU share mode removed

CPU sharing mode was introduced in 2.006 so that shared DirectX textures were still used but data was transferred to OpenGL via CPU.

In practice, performance was limited and could not be improved so this sharing mode is discontinued for 2.007.

Existing senders and receivers using CPU share mode will still communicate with 2.007 applications as long as the updated applications are using texture share mode.

# 1.6 Memory share mode improved

Performance of shared memory functions has been improved by using multiple pixel buffers to load from and upload to OpenGL textures and remains a backup where hardware is not texture share compatible.

## 2. New for 2.007

# 2.1 Spout Utilities

"SpoutUtils" is a namespace containing utility functions that are accessible by any application that includes the Spout SDK.

#### 2.1.1 Logging

Logging is introduced throughout the SDK to provide advisory, warning and error notices. Logs can be displayed in a console window or written to a file. You can also include your own logs.

Functions are broadly based on <u>Openframeworks logs</u> and are used in a similar manner.

Commented code examples are included in the Spout SDK openframeworks "ofSpoutExample" graphics sender application.

#### **Logging functions**

Often it is useful to open a console window during application development to output text messages. The console will only show what you print to it.

```
void OpenSpoutConsole();
```

You can close the console with an optional warning.

```
void CloseSpoutConsole();
```

You can also enable logging to see the logs generated within the Spout SDK.

```
void EnableSpoutLog();
```

Output is to a console window by default but you can instead, or additionally, specify output to a text file with the extension of your choice. The log file is re-created every time the application starts unless you specify to append to the existing one.

```
void EnableSpoutLog(const std::string filename, bool append = false);
```

The file is saved in the %AppData% folder (..\AppData\Roaming\Spout) unless you specify the full path. After the application has run you can find and examine the log file. This folder can also be opened in Windows Explorer directly from the application.

```
void ShowSpoutLogs();
```

Or the entire log can be returned as a string.

```
std::string GetSpoutLog();
```

You can set the level above which the logs are shown

```
SPOUT_LOG_SILENT - Disable all messages
SPOUT_LOG_VERBOSE - Show all messages
SPOUT_LOG_NOTICE - Notices
SPOUT_LOG_WARNING - Warnings
SPOUT_LOG_ERROR - Errors
SPOUT_LOG_FATAL - Fatal errors
SPOUT_LOG_NONE - Ignore log levels
```

For example, to show only warnings and errors:

```
SetSpoutLogLevel(SPOUT LOG WARNING);
```

or leave set to default Notice to see more information.

You can also create your own logs. For example:

```
SpoutLog("SpoutLog test"); // (equivalent to using SPOUT_LOG_NONE)
```

Or specify the logging level. For example:

```
SpoutLogNotice("Important notice");
Or
   SpoutLogFatal("This should not happen");
Or
   SetSpoutLogLevel(SPOUT_LOG_VERBOSE); // (default is SPOUT_LOG_NOTICE)
   SpoutLogVerbose("Message");
```

Logs can include strings, integers, float numbers etc. based on the "printf" notation. For example :

Finally you can disable logging at any time within your application.

```
DisableSpoutLog();
```

#### 2.1.2 SpoutMessageBox

There are situations, such as within a plugin, where a Windows MessageBox cannot be used because it would interfere with the application GUI and cause a freeze.

SpoutMessageBox can be used to avoid this problem in situations where you still need to draw the user's attention to a message. A timeout can also be specified so that the user does not need to dismiss the message.

You can use a simple version:

```
int SpoutMessageBox(const char * message, DWORD dwMilliseconds = 0);
```

or replace an existing MessageBox call with an alternative with standard arguments.

SpoutMessageBox uses "SpoutPanel.exe", usually used to display a sender list, so Spout must have been installed. If not, a standard, untimed, topmost messagebox is displayed.

#### 2.1.3 Registry utilities

Utility functions to read and write from the registry are now consolidated into SpoutUtils.

An "HKEY" argument has been added to make them more general purpose and the order of arguments has been revised.

# 2.2 Frame counting

Version 2.007 introduces frame counting which enables a receiver to detect the frame number and frame rate of a sender.

A named counting semaphore is used so that both sender and receivers connecting with it can access the count. Receivers compare the current sender count with the last. If it is the same, the receiver's shared texture is not updated to save processing time.

An application can avoid further re-processing of the received texture by using *IsFrameNew()* after receiving the frame. The receiver can also retrieve the sender frame count and received frame rate.

Frame counting can be enabled or disabled using "SpoutSettings" or by the application if necessary.

When disabled, sender/receiver communication is exactly the same as Spout 2.006 and earlier. If enabled, earlier applications are not affected.

If enabled, a 2.007 application can determine whether a sender produces a frame count with "GetSenderFrame()". Applications before 2.007 will return 0.

Independently of frame counting, a utility function is included to control the frame rate of a sender application if no other means is available. It is called for each render cycle to introduce the required delay.

```
void EnableFrameCount(const char* SenderName);// Application enable
void DisableFrameCount();// Application disable
bool IsFrameCountEnabled();// Application check status
bool IsFrameNew(); // Is the received frame new
double GetSenderFps(); // Received frame rate
long GetSenderFrame(); // Received frame count
void HoldFps(int fps); // Sender frame rate control
```

Other public functions are used by classes of the Spout SDK.

## 2.3 High level sender and receiver management

Sender and receiver classes now include high level functions that reduce complexity within the application, particularly for a receiver.

A new sender function "SendFboData" allows for sending a texture attached to the currently bound fbo. This is particularly useful if the sending texture is larger than the size that the sender is set up for.

This can be the case if the application is using only a portion of the allocated texture space, such as for Freeframe plugins. This was previously achieved by rendering to the shared texture using "DrawToSharedTexture".

Commented code examples are included in the Spout SDK Openframeworks "ofSpoutExample" sender and receiver applications.

#### 2.3.1 Sender

- 1) Create and allocate an RGBA texture or pixel buffer for sending.
- 2) Set up the sender

3) Update the sender for size changes

If the sending texture changes size, you need to update the sender with the new width and height.

```
void Update(unsigned int width, unsigned int height);
```

4) Send texture or pixel data

#### 5) Query the sender

At any time you can query the sender to retrieve the size, frame number and frame rate.

```
unsigned int GetWidth();
unsigned int GetHeight();
long GetFrame();
double GetFps();
```

6) Close the sender

At program termination, close the sender to free resources.

```
void CloseSender();
```

Once closed, the sender has to be set up again.

#### 2.3.2 Receiver

1) Create and allocate an RGBA texture or pixel buffer for receiving.

The size does not matter at this stage because it can be updated when the receiver connects to a sender.

2) Set up the receiver

This is optional because the receiving texture/buffer size can be reset when a sender update signal is received. But the option to flip the received texture can be set here - default is false. The function can be also used to reset the receiver if necessary.

Optionally you can specify the sender to connect to. The application will not connect to any other unless the user selects one, If that sender closes, the application will wait for the nominated sender to open.

```
void SetReceiverName(const char * SenderName);
```

3) Update the texture

At every cycle, before receiving texture data, you must check whether the sender size has changed from that of the receiving texture.

```
if(myReceiver.IsUpdated()) {
     .. update the receiving texture or buffer
}
```

#### 4) Optional: query the sender frame status

The receiving texture or pixel buffer is only refreshed if the sender has produced a new frame.

There is normally no performance gain for the application to determine whether the sender has produced a new frame before processing it unless the sender cycles more slowly than the receiver.

However, this can be done if required.

5) Receive the texture or pixel data

6) User sender selection

```
void SelectSender();
```

This function activates the executable program "SpoutPanel" that displays a dialog with a list of names for the currently running senders and allows the user to choose one.

#### 7) Query the sender

At any time you can retrieve the name, size, frame rate and number.

```
// Return the connected sender name
const char * GetSenderName();
// Return the connected sender width
unsigned int GetSenderWidth();
// Return the connected sender height
unsigned int GetSenderHeight();
// Return the connected sender frame rate
double GetSenderFps();
// Return the connected sender frame number
long GetSenderFrame();
```

#### 8) Close the receiver

At program termination, close the receiver to free resources.

```
void CloseReceiver();
```

#### 2.4 Lower level functions

Earlier functions for sender and receiver management have not been changed and can still be used as detailed in the Spout 2.006 documentation.

There may be situations where lower level functions are necessary and documentation can be revised accordingly. Hopefully these will show up during beta testing and your feedback is valuable to help guide the documentation.

# 2.5 Summary of 2.007 sender and receiver functions

Sender

```
// Set up starting values for a sender
bool SetupSender(const char* SenderName, unsigned int width,
      unsigned int height, bool bInvert = true, DWORD dwFormat = 0);
// Update sender dimensions
void Update(unsigned int width, unsigned int height);
// Close sender and release resources
void CloseSender();
// Send texture data
bool SendTextureData(GLuint TextureID, GLuint TextureTarget,
      GLuint HostFbo = 0);
// Send texture data attached to an fbo
bool SendFboData(GLuint FboID);
// Send pixel data
bool SendImageData(const unsigned char* pixels,
      GLenum glFormat = GL_RGBA, GLuint HostFbo = 0);
// Return sender width
unsigned int GetWidth();
// Return sender height
unsigned int GetHeight();
// Return sender frame number
long GetFrame();
// Return sender frame rate
double GetFps();
// Sender frame rate control
void HoldFps(int fps);
```

#### Receiver

```
// Set up starting values for a receiver
void SetupReceiver(unsigned int width, unsigned int height,
      bool bInvert = false);
// Set the sender name to connect to
void SetReceiverName(const char * SenderName);
// Receive texture data
bool ReceiveTextureData(GLuint TextureID, GLuint TextureTarget,
      GLuint HostFbo = 0);
// Receive pixel data
bool ReceiveImageData(unsigned char *pixels,
      GLenum glFormat = GL_RGBA, GLuint HostFbo = 0);
// Return whether the connected sender has changed
bool IsUpdated();
// Return whether connected to a sender
bool IsConnected();
// Close receiver and free resources
void CloseReceiver();
// Open the user sender selection dialog
void SelectSender();
// Return the connected sender name
const char * GetSenderName();
// Return the connected sender width
unsigned int GetSenderWidth();
// Return the connected sender height
unsigned int GetSenderHeight();
// Return the connected sender frame rate
double GetSenderFps();
// Return the connected sender frame number
long GetSenderFrame();
// Return whether the received frame is new
bool IsFrameNew();
```

# 3. SpoutLibrary

SpoutLibrary, a library that can be used with C++ compilers other than Visual Studio, has been revised to enable all functions of the Sender and Receiver classes as well as access to utility functions in the SpoutUtils namespace.

The project is now comprised of four files:

SpoutLibrary.h SpoutLibrary.cpp SpoutFunctions.h SpoutFunctions.cpp

The project will build for 32 bit or 64 bit using Visual Studio 2017.

The resulting library files in either case are SpoutLibrary.dll and SpoutLibrary.lib. When using these in an application only the SpoutLibrary.h header file is required.

The original example for CodeBlocks is out of date and will be removed and replaced by an example for Visual Studio that can be maintained.

There are no examples for other compilers, but the library has been tested with QT / MingW for both 32 and 64 bit.

# 4. DirectX examples

Although Spout is designed around OpenGL, it can also be used for DirectX applications. However, there have been no code examples included with the Spout SDK.

More recently, tutorials originally shipped in the legacy DirectX SDK, have been updated by <u>Chuck Walbourn</u> for DirectX 11.

"Tutorial 04" has been modified as a Spout sender and "Tutorial 07" as a receiver.

The examples require only a sub-set of the Spout SDK:

```
SpoutSenderNames // for sender creation and update
SpoutSharedMemory // for sender name management
SpoutDirectX // for creating a shared texture
SpoutFrameCount // for mutex lock and new frame signal
SpoutUtils // for logging utilites
```

The modifications can be found by search on "Spout". They are minimal in order to work with the samples but should provide a guide for other DirectX 11 applications.

# 5. SpoutCam

SpoutCam has been extensively revised thanks to the work of Valentin Schmidt who created a <u>GitHub project</u> incorporating the DirectShow base classes and build configurations for both 32 bit and 64 bit for Visual Studio 2017. Without his help, SpoutCam could not have been updated.

His other <u>DirectShow projects</u>, including SpoutGrabber, SpoutRenderer, equivalents for <u>Newtek NDI</u> as well as encoder/decoder and renderer for HAP video should also be mentioned.

Now SpoutCam is available for both 32 bit and 64 bit host programs and can be maintained using Visual Studio 2017.

# 5.1 SpoutCamSettings

"SpoutCamSettings" allows SpoutCam frame rate and dimensions to be set as a typical webcam to assist with compatibility.

For 2.007, the program has been updated to allow register/un-register of SpoutCam.

Registration is normally done by the Spout installation with an option to register or not. These changes avoid the need for re-installation or manual registration if conflict is found with an application that only needs temporary resolution.